Atlas Update Procedure

Requirements

- PC Running Windows 7 or later.
- Micro USB B to USB A cable (Supplied with product).
- <u>Download</u> the latest firmware update program (This includes both the latest firmware and Log Fix software)
- Ensure that any anti-virus software is disabled before beginning the update procedure (The update process requires copying data to/from a USB device causing false threat alerts in anti-virus software).

<u>Instructions</u>

1. Ensure that the device is at least 50% charged & on the ground screen displaying the current time/date, temperature, battery level, etc.



- 2. Plug the device into PC.
- 3. Locate downloaded 'Alti-2LogFix.zip' file & extract it to a new folder. Once extracted there will be a single application called 'Alti-2LogFix.exe'.



4. Right click on the application and 'Run as administrator'.



5. Click the red 'Alti-2' circle button & follow the on-screen instructions. (The software will then locate any existing logs and update them, then will proceed to update the device firmware, which requires user input)



• When the device is connected to a PC it will enter USB mode and display 'Transferring Data to the Host' - This is normal.



- The software can take a while depending on the number of logs stored on the device, it may appear to have got stuck, however this is part of the update/logfix process.
- 6. When prompted via the on-screen instructions, unplug the Atlas unit and navigate to **Menu > System Admin > SW Reset**.





 With OK highlighted, click the middle button once then immediately press and hold the top & bottom buttons for 5 seconds. (This will put the device into 'firmware update mode')





- To check that the device is in firmware update mode: After Step 7, press either the top
 or bottom button a few times, this should result in the device being unresponsive This
 is normal.
- 8. Plug the device back into PC.
- 9. Once the software has finished updating the device will reboot to the startup screen and will display the latest firmware release number. Wait for the update software to display '**Update Completed**' before disconnecting.